Watch a video of this Sew Easy online at FonsandPorter.com/VUnits



"V" Block Units


Use Deb Tucker's V Block tool to make perfect V Units for *Tribute*.


NOTE: Instructions included with the V Block tool have measurements for cutting different size units. Each unit size also has a strip size listed that will give you fabric pieces slightly oversized.


For Tribute, the Side Unit FINISHED SIZE is $3" \times 3"$.


CUTTING CENTER TRIANGLES

- **1.** Layer fabric strips no more than 2 layers deep.
- **2.** Fold ends and finger-press to accommodate the slanted cut for your chosen size unit *(Photo A)*.
- **3.** Position tool so dashed line (Fold Line for Center Triangle) is aligned with the fold and the correct-size line of tool is along bottom edge of strip (*Photo B*).
- **4.** Cut along the slanted edge of tool. Unfold Center Triangles (*Photo C*). Discard end piece.
- 5. Flip strip over; align Center Triangle Trim Line with previously trimmed edge and cut next pair of Center Triangles (*Photo D*). Repeat to cut required number of Center Triangles.









CUTTING SIDE TRIANGLES

- Stack 2 strips with wrong sides facing and raw edges aligned. Straighten 1 end of stacked strips.
- **2.** Position tool with bold solid line (Cut Line for Side Triangles) aligned with trimmed end, with the correct-size line of tool along bottom edge of strip (*Photo E*).
- **3.** Cut along the slanted edge of tool to make 1 Side Triangle and 1 Side Triangle reversed.
- **4.** Rotate the tool; align angled line of tool with previously cut slanted edge and cut along straight edge of tool (*Photo F*). Repeat to cut required number of Side Triangle pairs.





FonsandPorter.com

V UNIT ASSEMBLY

- **1.** Lay out 1 Center Triangle, 1 Side Triangle, and 1 Side Triangle reversed as shown in *Photo G*.
- 2. Join Side Triangle to Center Triangle as shown in *Photo H*. Press seams away from Center Triangle. Repeat to join Side Triangle reversed to Center Triangle (*Photo I*).
- **3.** Trim 2 edges of unit using the tool, aligning the FINISHED SIZE measurement on the tool with the seam lines *(Photo J)*.
- **4.** Rotate unit and reposition tool, aligning CUT SIZE measurement on the tool with previously trimmed sides and "X" with sewn seam intersection *(Photo K).* Trim remaining edges to complete 1V Unit *(Photo L).*

NOTE: Cut size (Trim Size) of unit is $\frac{1}{2}$ " larger than the finished size.

